

LiquidLib

A comprehensive tool for post processing of liquid molecular dynamic simulations

1 Introduction

LiquidLib is a open source package to compute the following quantities:

- [Pair Distribution Function](#)
- [Structure Factor](#)
- [Mean Squared Displacement](#)
- [Non-Gaussian Parameter](#)
- [Four Point Correlation](#)
- [Velocity Auto Correlation](#)
- [Self van Hove Correlation](#)
- [Coherent van Hove Correlation](#)
- [Self Intermediate Scattering Function](#)
- [Coherent Intermediate Scattering Function](#)
- [Bond Order Parameter](#)

2 Acknowledgments

LiquidLib is an open source code and is published under the MIT License. The core contributors are Zhikun Cai, Abhishek Jaiswal, Nathan Walter, and Yang Zhang.

If you distribute a modified code or release any of the source code that includes *LiquidLib* source files then it must also be open sourced. Anyone is free to use modify or extend. This has been a joint effort by Zhang research group at University of Illinois at Champaign-Urbana. More information can be found at <http://zhang.npre.illinois.edu/>. Contact information for any of the contributors can also be found at the former address, any issues, bugs, or other related material can be sent to us via our contact information listed at the group webpage.

Please cite as:

Zhikun Cai, Abhishek Jaiswal, Nathan Walter, Yang Zhang. *LiquidLib User Manual v0.2* <http://zhang-group.github.io/LiquidLib/>

3 Installation

To make a quick and basic installation of *LiquidLib*, begin by opening a terminal window.

```
$ mv liquidlib.tar.gz /installation/directory/  
$ cd /installation/directory/  
$ tar -zxvf liquidlib.tar.gz  
$ cd liquidlib  
$ make
```

This will create a directory `/liquidlib/bin/` with all of the executables contained within it.

To make a GROMACS compatible build, open Makefile and in the optional components section change "USE_XDRLIB" to "yes". This will add the appropriate flags for *LiquidLib* to be built to read .xtc and .trr trajectory files. Follow the instructions in Makefile for linking the xdrfile headers to make a build that can read trajectories that are dumped as .trr or .xtc binary files, such as GROMACS does,

or .xtc for LAMMPS. In order to read these file types, LiquidLib relies on the open source library libxdrfile. The source code can be downloaded from the GROMACS website or the following link: <ftp://ftp.gromacs.org/pub/contrib/xdrfile-1.1.1.tar.gz> Newer versions of the xdrfile library should be compatible with LiquidLib, however, we recommend 1.1.1 as this is the version used for testing purposes.

Once libxdrfile.a and xdrfile.h, xdrfile_trr.h, and xdrfile_xtc.h have been installed, open the *LiquidLib* Makefile, and edit the lines contained in the comment section for the GROMACS build. For compiling, the libxdrfile.a and xdrfile.h, xdrfile_trr.h, and xdrfile_xtc.h headers can be placed inside of the *LiquidLib* include directory, or you can specify the location inside of the Makefile. Recompile LiquidLib and the binaries should be compatible with GROMACS.

To build parallelized OpenMP support, open Makefile in a text editor and in the optional components section change "USE_OMP" to "yes". This will add the appropriate flags for *LiquidLib* to be built with OpenMP support included. Recompile the program thereafter.

In order for the bond order parameter calculation to be performed, *LiquidLib* requires either Boost or GSL to be installed. Once one of these has been installed, in the makefile switch either USE_BOOST or USE_GSL to "yes," if both are set to yes, then GSL will be used with priority.

All user options for the Makefile are listed at the beginning of the Makefile.

4 Description of Quantities

This section provides a brief overview of the quantities, including operating equations. Please refer to standard textbooks, journal articles for explanation of physical meaning, and how to interpret your results. The quantities can be weighted by the appropriate scattering lengths (coherent or incoherent) if the user wants to compare to experimentally measurable quantities.

4.1 Pair Distribution Function: $g(r)$

For an isotropic and homogenous liquid system, the pair distribution function (PDF) or radial distribution function (RDF), depends only on the modulus of relative atomic distance and can be computed as follows:

$$g(r) = \frac{1}{4\pi r^2 dr \rho N \langle b_{coh} \rangle^2} \left\langle \sum_{l \neq l'} b_l b_{l'} \delta(\mathbf{r} - |\mathbf{r}_l - \mathbf{r}_{l'}|) \right\rangle. \quad (1)$$

where r is the distance between two particles, ρ is the particle density, N is the number of particles, and b is the coherent scattering length, where $\langle \rangle$ represents the average of the values.

4.2 Structure Factor: $S(k)$

The static structure factor $S(k)$ is a quantity that can be directly measured by scattering experiments such as with neutrons or X-rays. For an isotropic system there are no preferred orientation and hence the structure factor depends only on the modulus of the wave vector transfer k . The experimentally measured structure factor by neutrons is weighed by the proper coherent bound neutron scattering lengths ' b ' and needs to be factored in when computing the total $S(k)$ of the system as shown:

$$S(k) = \frac{1}{N \langle b \rangle^2} \left\langle \sum_{l, l'=1}^N b_l b_{l'} \exp \{ -i \mathbf{k} \cdot [\mathbf{r}_l - \mathbf{r}_{l'}] \} \right\rangle. \quad (2)$$

A simplified representation of $S(k)$ is shown in Eq. [3]. In performing the computations of $S(k)$, the computational complexity of Eq. [2] is reduced to $\mathcal{O}(N)$ by performing angular average over preferred directions

at a given k -value.

$$S(k) = \frac{1}{N\langle b_{coh} \rangle^2} \left\langle \left[\sum_{l=1}^N b_l \cos(\mathbf{k} \cdot \mathbf{r}_l) \right]^2 + \left[\sum_{l=1}^N b_l \sin(\mathbf{k} \cdot \mathbf{r}_l) \right]^2 \right\rangle. \quad (3)$$

4.3 Mean Squared Displacement: $\langle r^2(t) \rangle$

The mean-squared displacement of particles at an elapsed time ‘ t ’ is related to the second moment of the self van Hove correlation function. Typically for liquids, particle will show ballistic motions at very short times, followed by particle collisions resulting in a plateau, and eventually undergo random walk.

$$\langle r^2(t) \rangle = \frac{1}{N} \left\langle \sum_{l=1}^N |\mathbf{r}_l(t) - \mathbf{r}_l(0)|^2 \right\rangle. \quad (4)$$

4.4 Non-Gaussian Parameter: $\alpha_2(t)$

The non-Gaussian parameter measures the deviation from the gaussian behavior of particles. It is commonly used as a measure of dynamic heterogeneity in the system. For brownian diffusion $\alpha_2(t) = 0$. If all particles have same displacement then it takes the theoretical minimum of -2/5. When there is heterogeneity in particle displacements, then $\alpha_2(t) > 0$. It can be computed as follows:

$$\alpha_2(t) = \frac{3 \left\langle \sum_{l=1}^N [\mathbf{r}_l(t) - \mathbf{r}_l(0)]^4 \right\rangle}{5 \left\langle \sum_{l=1}^N [\mathbf{r}_l(t) - \mathbf{r}_l(0)]^2 \right\rangle^2} - 1. \quad (5)$$

4.5 Four Point Correlation: $\chi_4(t)$

Direct quantification of a length scale characterizing correlated particles motion in liquids involves the motion of two or more particles, and hence are probed using a four-point, time-dependent density correlation functions that contain information about the density at two spatial points and two times. To capture the correlated motions between particles in liquids, we utilize a ‘coarse graining’ approach by using an ‘overlap’ function that measures overlap between configurations at time $t = 0$ and a future time t . The overlap function $w(|r_1 - r_2|)$ is unity for $|r_1 - r_2| \leq a$ and 0 otherwise. The distance parameter ‘ a ’ is chosen to be larger than the square root of the plateau of $\langle r^2(t) \rangle$. The program doesn’t normalize by the temperature as this input is not provided in the trajectory or user input file. Hence the user must do this in post-processing.

$$\begin{aligned} \chi_4(t) &= \frac{V}{T} [\langle Q_s^2(t) \rangle - \langle Q_s(t) \rangle^2], \\ Q_s(t) &= \frac{1}{N} \sum_{l=1}^N w(|\mathbf{r}_l(t) - \mathbf{r}_l(0)|). \end{aligned} \quad (6)$$

4.6 Velocity Auto Correlation: $C_{vv}(t)$

Velocity auto correlation function is a statistical correlation between particle velocities at two points in time, 0 and some later time ‘ t ’. It can be used to measure the self-diffusion coefficient or the vibrational properties of a given system.

$$C_{vv}(t) = \frac{1}{\langle b^2 \rangle} \langle b_i \mathbf{v}_i(0) \cdot b_i \mathbf{v}_i(t) \rangle \quad (7)$$

4.7 Self van Hove Correlation: $G_s(r, t)$

Single particle's motion can be studied using the self-part of the van Hove correlation function. In the liquid state, the system is isotropic and hence this quantity depend only on the magnitude of displacements not their directions. The physical meaning of $G_s(r, t)$ is the probability of finding a particle i in the vicinity of some distance ' r ' at some other time ' t ' given that it was at origin at $t = 0$.

$$G_s(r, t) = \frac{1}{N\langle b_{inc}^2 \rangle} \left\langle \sum_{l=1}^N b_l^2 \delta(\mathbf{r} + \mathbf{r}_l(0) - \mathbf{r}_l(t)) \right\rangle. \quad (8)$$

4.8 Coherent van Hove Correlation: $G(r, t)$

The coherent van Hove correlation function is a measure of the density-density correlations at two spatial points as a function of time. In the liquid state, the system is isotropic and hence this quantity depend only on the magnitude of displacements, but not their directions. One can separate this function into two parts, self and distinct. The physical meaning of this function is the probability density of finding a particle i in the vicinity of \mathbf{r} at a given time t knowing that another particle j is in the vicinity of the origin at time $t = 0$. In the long time limit, the system loses memory of its initial configuration and this the correlation function becomes independent of the distance \mathbf{r} .

$$G(r, t) = \frac{1}{N\langle b_{coh} \rangle^2} \left\langle \sum_{l=1}^N \sum_{l'=1}^N b_l b_{l'} \delta(\mathbf{r} + \mathbf{r}_l(0) - \mathbf{r}_{l'}(t)) \right\rangle. \quad (9)$$

4.9 Self Intermediate Scattering Function: $F_s(k, t)$

Self Intermediate Scattering Functions (SISF) is defined as the spatial Fourier transform of $G_s(r, t)$ to the reciprocal space, which can be measured either directly by correlation spectroscopy and neutron spin echo technique. SISF characterizes the density fluctuations of the same particle in the system at time $t = 0$ and at another subsequent time t . The incoherent neutron scattering arising from isotopic variations and/or spin fluctuations provides a measure of the self-intermediate scattering function.

$$F_s(k, t) = \frac{1}{N\langle b_{inc}^2 \rangle} \left\langle \sum_{l=1}^N b_l^2 \exp \{-i\mathbf{k} \cdot [\mathbf{r}_l(t) - \mathbf{r}_l(0)]\} \right\rangle. \quad (10)$$

4.10 Coherent Intermediate Scattering Function: $F(k, t)$

Coherent Intermediate Scattering Functions (CISF) is defined as the spatial Fourier transform of $G(r, t)$ to the reciprocal space, which can be measured either directly by correlation spectroscopy and neutron spin echo technique, or indirectly by inelastic scattering experiments.

$$F(k, t) = \frac{1}{N\langle b_{coh} \rangle^2} \left\langle \sum_{l=1}^N \sum_{l'=1}^N b_l b_{l'} \exp \{-i\mathbf{k} \cdot [\mathbf{r}_l(t) - \mathbf{r}_{l'}(0)]\} \right\rangle. \quad (11)$$

4.11 Bond Order Parameter: $q_l(i, t)$, $\bar{q}_l(i, t)$, $Q_l(t)$

Bond Order Parameter is a quantity for measuring medium range order in a system. q is the bond order parameter for an individual atom, Q is the system wide bond order parameter, l is the order of the bond order parameter (typical values are 4 and 6), i is the atom number, t is the time. This quantity cannot be compared to experiments but can be very useful for determining structural order and phases in a system. The quantities are defined as below

$$q_{lm}(i, t) = \frac{1}{N(i)} \sum_{j=1}^{N(i)} Y_{lm}(\hat{r}_{ij}(t)) \quad (12)$$

where m ranges from $-l$ to l , $N(i)$ is the number of nearest neighbors around atom i , and Y_{lm} is the spherical harmonic of order l and m , and \hat{r}_{ij} is the unit vector between atom i and j . The unit vector can be converted to spherical coordinates which are required for the spherical harmonics

$$q_l(i, t) = \sqrt{\frac{4\pi}{2l+1} \sum_{m=-l}^l |q_{lm}(i, t)|^2} \quad (13)$$

this is the bond order parameter per atom.

$$Q_{lm}(t) = \frac{\sum_{i=1}^N N(i) q_{lm}(i, t)}{\sum_{i=1}^N N(i)} \quad (14)$$

where N is the number of atoms in the system.

$$Q_l(t) = \sqrt{\frac{4\pi}{2l+1} \sum_{m=-l}^l |Q_{lm}(t)|^2} \quad (15)$$

This is the bond order parameter of the system

$$\bar{q}_{lm}(i, t) = \frac{1}{N(i)} \sum_{j=0}^{N(i)} q_{lm}(j, t) \quad (16)$$

and

$$\bar{q}_l(i, t) = \sqrt{\frac{4\pi}{2l+1} \sum_{m=-l}^l |\bar{q}_{lm}(i, t)|^2} \quad (17)$$

this is the nearest neighbor averaged bond order parameter. Lastly,

$$\bar{Q}_l(t) = Q_l(t) \quad (18)$$

there is no difference between the system bond order parameter and the nearest neighbor averaged system bond order parameter.

5 Execution

LiquidLib provides source code to several binaries. Each binary is designed to calculate one quantity. To calculate a quantity, one must provide an input file. The input file contains all of the parameters, essential and optional, necessary for *LiquidLib* to compute the respective quantity. By default, *LiquidLib* executables search the current directory for the input file with the abbreviation for the quantity with the file extension .in. Similarly, when the quantity is written to file, the file is named by default the quantity abbreviation .txt, and is placed in the current directory. The following list summarizes the default file names used.

- | | |
|--|---|
| <ul style="list-style-type: none"> • Pair Distribution Function:
g_r.in
g_r.txt | <ul style="list-style-type: none"> • Non-Gaussian Parameter:
alpha2_t.in
alpha2_t.txt |
| <ul style="list-style-type: none"> • Structure Factor:
S_k.in
S_k.txt | <ul style="list-style-type: none"> • Four Point Correlation:
chi4_t.in
chi4_t.txt |
| <ul style="list-style-type: none"> • Mean Squared Displacement:
r2_t.in
r2_t.txt | <ul style="list-style-type: none"> • Velocity Auto Correlation:
vacf_t.in
vacf_t.txt |

- | | |
|---|---|
| • Self van Hove Correlation: | Fs.kt.txt |
| Gs_rt.in | |
| Gs_rt.txt | |
| • Coherent van Hove Correlation: | |
| G_rt.in | F_kt.in |
| G_rt.txt | F_kt.txt |
| • Self Intermediate Scattering Function: | |
| Fs_kt.in | |
| | • Coherent Intermediate Scattering Function: |
| | F_kt.in |
| | F_kt.txt |
| | • Bond Order Paramter: |
| | BOP.in |
| | BOP.txt |

While these are the default files that will be used by *LiquidLib*, the file names used are ultimately up to the user. The user may use any input and output name they please. To use a non-default input name, the file used must be specified during command line operation, and to use a non-default output name, the file used must be specified in the input file under the option `outputfilename`. The command line operation to compute a quantity (for example `MeanSquaredDisplacement`) is as follows:

```
$ cd /execution/directory/
$ /installation/directory/bin/computeMeanSquaredDisplacement -i user_msd_file.in
```

where “-i user_msd_file.in” is not needed if the input file is the default *r2_t.in*. If execution is successful, the program will print “Successfully computed Mean Squared Displacement”. If execution is not successful, various WARNINGS and ERRORS will be printed to screen. The user should refer to the [Common Errors](#) section for solutions to the problem. For the options that may be used in the input file please refer to the [Input Parameters](#) section below.

6 Input Parameters

This section of the manual describes the potential options that can be used in the input files. The first subsection [Trajectory Parameters](#) shows the options that are universal to all of the codes, and the following sections show options that are special to that quantity. Only options listed as *mandatory* are required for operation of any given quantity. All other inputs are optional since a default value is provided, however, it is recommended that the user set those values to their needs.

6.1 Trajectory Parameters

#

Marks a comment in the input file. Entire lines or ends of lines may be comments.

=

Can be used after a parameter name for aesthetic purposes. A trailing space must be used after a = in order for the values to be correctly determined from the input file.

is_run_mode_verbose

- [default: false, optional] false, no, or 0 informs the program to run in a concise mode.
- true, yes, or a non-zero number informs the program to run in a verbose mode and keep flushing the progresses of reading trajectory and computation. One can also turn on the verbose mode by adding a flag “-v” behind the execution command. The value in input file will overwrite this “-v” option, if they disagree.

is_wrapped

- [default: false, optional] false, no, or 0 informs the program that the trajectory is unwrapped.
- true, yes, or a non-zero number informs the program that the trajectory is wrapped in a periodic box and thus needs to be unwrapped in order to produce correct values for dynamic quantities. If set to true, LiquidLib will unwrap the coordinates before computation.

start_frame

- [default: 0, optional] This value determines the first frame number to read from the trajectory. If this option is set, *LiquidLib* will skip the frames prior to this number. This is useful when using an unequilibrated trajectory and the user wishes to skip the unequilibrated portion of the trajectory.

end_frame

- [default: 0, optional] This value determines when the last frame that will be read from the trajectory file. This parameter is optional and will be overwritten by other parameters such as start_frame, frame_interval, and number_of_frames_to_average during the computation. User must provide either end_frame or number_of_frames_to_average (preferred) in their scripts.

dimension

- [default: 3, optional] This value determines the dimension of the trajectory. LAMMPS can provide 2-d and 3-d trajectories. GROMACS and VASP can provide 3-d trajectories. However, *LiquidLib* is capable of calculating the quantities in any finite dimension when supplied with a such a trajectory, such as the trajectories created by our groups' any dimensional md package.

trajectory_delta_time

- [default: 1, optional] This value determines the Δt between frames in the trajectory. For GROMACS, this value can be determined from the trajectory file. However, for other programs, such as LAMMPS, VASP, or other trajectory sources, this parameter is not determined automatically from the trajectory. Thus, for time dependent quantities, such as mean squared displacement or intermediate structure factor, the trajectory Δt is required for proper output time_scale provided by user. If this parameter is not provided, the time step will be set to 1 (a.u.), or equivalently 1 step.

output_file_name

- [default: see [here](#) for defaults, optional] This value sets the name and location for the output data to be written to. Only condition on the location of outputfile is the directory must exist prior to execution as *LiquidLib* will not create the directory.

trajectory_file_name

- [**mandatory**] This option sets the name and location of the trajectory file. As of now, the only file types that are recognized for reading the trajectory are .trr, .xtc, .xyz, .dump, .atom, and XDATCAR. dump and atom extensions are for LAMMPS trajectories and XDATCAR is for VASP. .trr and .xtc can only be read if *LiquidLib* is built in GROMACS compatible mode.

trajectory_file_type

- [optional] This option can be set to "abc" in order to signal to the program that a ABC trajectory is being read in. ABC trajectories are produced by a module created in GROMACS by our research group. ABC is also only usable with bond order parameter, since there is no time in ABC trajectories.

trajectory_data_type

- [default: coordinate, optional] This sets the type of information that will be read from the trajectory file. For .trr files, this will change how the file is read. This needs to be set to velocity for VACF.

gro_file_name

- [**Conditionally Required in GROMACS mode**] This sets the name and location of the .gro file for GROMACS trajectories. This is needed to determine the atom types and groups in the system. If the trajectory is monatomic or one wishes to compute a quantity for the entire system, this does not need to be provided. However, if the user wants to compute a quantity for a specific atom type or group from a GROMACS trajectory, this is required.

atom_types

- [default: empty, mandatory] This sets the type of atom that will be focused on for the computation. For example, if user wishes to compute the mean squared displacement of only hydrogen this can be set to H. The atom_type value should be compatible with the types used in trajectory file. Can be a letter for GROMACS, VASP, LAMMPS trajectories, or a number for LAMMPS trajectories. We now

support multiple atom types, for example a user may request both Hydrogen and Oxygen by specifying HW OW

scattering_lengths

- [default: 1, optional] This sets the scattering lengths for the atom types request from atom_types. The order of the scattering lengths must be provided in the same order as the atom types were in order for the scattering lengths to be paired correctly to their corresponding atom type. This parameter is used for weighting quantities based on the scattering lengths so that the quantity is more readily comparable to scattering experiments.

atom_group

- [default: "system", optional] Only useful for trajectories, where groups of atoms exists. This parameter sets if the computation is performed on particular type(s) of atom from the whole system [default], or a sub group such as the solvent [solvent], or protein [protein] or, or non-solvent [non-solvent].

number_of_frames_to_average

- [default: 1, optional] This parameter sets the number of frames that will be used to average with. For example, if set to N frames, this quantity will use N unique frames to compute the value of the static quantities, i.e. will use N frames to calculate the radial distribution function. Or, for dynamic quantities, N frames will be used to average the value at every time point, i.e. N frames will be used to average the mean squared displacement at each time point t .

output_precision

- [default: 15, optional] This parameter sets the scientific precision of the output file.

6.2 Pair Distribution Function: $g(r)$

User can input two atom types using the **atom_types1** and **atom_types2** parameters listed below. If the scattering lengths are provided then, they are appropriately weighted. If no value is provided then it is set to 1.

atom_types1

- [default: empty, mandatory] This parameter sets the first atom types being studied. By default, the program requires atom types to be provided in order for computation to proceed. But this parameter can be set to the atom identifier used in the trajectory or .gro file, i.e. HW for hydrogen in water, or Li for lithium, or 1 if the atom type is numeric in the trajectory. Can also be set to multiple atom types.

atom_types2

- [default: empty, mandatory] The parameter sets the second types being studied. If this parameter is not set, the program requires atom types to be provided in order for computation to proceed.

atom_group

- [default: "system", optional] This parameter can be set if user wants only the atomtype to be from a sub-group solvent[solvent]. The options available are system, solvent, and non-solvent

atom_group2

- [default: equal to atomgroup, optional] This parameter can be set if user wants only the atomtype2 to be from a sub-group solvent[solvent]. The options available are system, solvent, and non-solvent

number_of_bins

- [default: 200, optional] This value sets the number of spatial ($|r|$) bins used between 0 and maxcut-offlength.

max_cutoff_length

- [default: half of the smallest box side] This value sets the max $|r|$ used for $g(r)$. By default this value will be set to the smallest boxlength in any dimension. If a max value greater than half the smallest boxlength is provided, the value will be reset to the half the smallest boxlength as spatial correlations for values of $|r|$ greater than half of box length cannot be accurately determined and thus should not be used.

6.3 Structure Factor: $S(k)$

User can input selected atom types using only the **atom_types** parameter. Scattering lengths can be provided in the same order of atom types in order to compute the total structure factor comparable to experiments.

k_start_index

- [default: 0, optional] This value determines the first multiple of δk used, where $\delta k = 2*\pi/\text{boxlength}$.

number_of_bins

- [default: 50, optional] This sets the number of multiples of δk where structure factor will be computed starting from **k_start_index** and ending at **k_start_index** + **number_of_bins**.

number_of_kvectors

- [default: 1, optional] This value sets the number of directional **k** vectors sampled for every value of $|k|$.

6.4 Mean Squared Displacement: $\langle r^2(t) \rangle$

The binary to compute Mean Squared Displacement is `/bin/computeMeanSquaredDisplacement`. User can input selected atom types using only the **atom_types** parameter. The options that can be included in the input file in addition to those listed in [Trajectory Parameters](#) are as follows:

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the mean squared displacement. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Mean squared displacement can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the **time_scale** is set to “linear”, this value should be an integer greater than or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the mean squared displacement to be computed every .2 ps, this value should be set to 2.
- If the **time_scale** is set to “log”, this value determines the base of the scaling for calculating the mean squared displacement. For example, if this value is set to 1.5, then the mean squared displacement will be computed at nearest rounded integer time points $0, 1.5^0(1), 1.5^1(2), 1.5^2(2), 1.5^3(3), \dots, 1.5^n$.

6.5 Non-Gaussian Parameter: $\alpha_2(t)$

User can input selected atom types using only the **atom_types** parameter.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the non-Gaussian parameter. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Non-Gaussian parameter can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the `time_scale` is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the non-Gaussian parameter to be computed every .2 ps, this value should be set to 2.
- If the `time_scale` is set to “log”, this value determines the base of the scaling for calculating the non-Gaussian parameter. For example, if this value is set to 1.5, then the non-Gaussian parameter will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

6.6 Four Point Correlation: $\chi_4(t)$

User can input selected atom types using only the **atom_types** parameter.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the four point correlation function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output, four point correlation function can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the `time_scale` is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the four point correlation function to be computed every .2 ps, this value should be set to 2.
- If the `time_scale` is set to “log”, this value determines the base of the scaling for calculating the four point correlation function. For example, if this value is set to 1.5, then the four point correlation function will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

overlap_length

- [**mandatory**] This value sets the overlap length. It is usually set to the square root of the plateau of the mean squared displacement so as to filter out vibrations. For more information on this parameter and how to set the value, please refer to N. Lacevic, F. W. Starr, T. B. Schroder, S. C. Glotzer, “Spatially heterogeneous dynamics investigated via a time-dependent four-point density correlation function,” J. Chem. Phys. 119, 7372 (2003).

6.7 Velocity Auto Correlation: $C_{vv}(t)$

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the velocity auto correlation. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Velocity auto-correlation can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps). We recommend usage of linear scale for future Fourier transform needs.

frame_interval

- [default: 1, optional] This value has two meanings. If the `time_scale` is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point

to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the velocity auto-correlation function to be computed every .2 ps, this value should be set to 2.

- If the `time_scale` is set to “log”, this value determines the base of the scaling for calculating the velocity auto-correlation function. For example, if this value is set to 1.5, then the velocity auto-correlation will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

6.8 Self van Hove Correlation: $G_s(r, t)$

User can input selected atom types using only the **atom_types** parameter.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the self van Hove correlation function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Self van Hove correlation can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the `time_scale` is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the self van Hove correlation function to be computed every .2 ps, this value should be set to 2.

- If the `time_scale` is set to “log”, this value determines the base of the scaling for calculating the self van Hove correlation function. For example, if this value is set to 1.5, then the self van Hove correlation will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

number_of_bins

- [default: 200, optional] This value determines the number of spatial ($|r|$) bins used between 0 and `max_cutoff_length` to sample the self van hove correlation.

max_cutoff_length

- [default: half of the smallest box side] This value sets the max $|r|$ used for $g(r)$. By default this value will be set to the smallest boxlength in any dimension. If a max value greater than half the smallest boxlength is provided, the value will be reset to the half the smallest boxlength as spatial correlations for values of $|r|$ greater than half of box length cannot be accurately determined and thus should not be used.

6.9 Coherent van Hove Correlation: $G(r, t)$

User can input selected atom types using only the **atom_types** parameter. Scattering lengths can be provided in the same order of atom types.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the coherent van Hove correlation function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Self van Hove correlation can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the time_scale is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the self van Hove correlation function to be computed every .2 ps, this value should be set to 2.
- If the time_scale is set to “log”, this value determines the base of the scaling for calculating the self van Hove correlation function. For example, if this value is set to 1.5, then the self van Hove correlation will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

number_of_bins

- [default: 200, optional] This value determines the number of spatial ($|r|$) bins used between 0 and max_cutoff_length to sample the self van hove correlation.

max_cutoff_length

- [default: half of the smallest box side] This value sets the max $|r|$ used for $g(r)$. By default this value will be set to the smallest boxlength in any dimension. If a max value greater than half the smallest boxlength is provided, the value will be reset to the half the smallest boxlength as spatial correlations for values of $|r|$ greater than half of box length cannot be accurately determined and thus should not be used.

6.10 Self Intermediate Scattering Function: $F_s(k, t)$

User can input selected atom types using only the **atom_types** parameter.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the self intermediate scattering function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Self intermediate scattering function can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the time_scale is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the self intermediate scattering function to be computed every .2 ps, this value should be set to 2.
- If the time_scale is set to “log”, this value determines the base of the scaling for calculating the self intermediate scattering function. For example, if this value is set to 1.5, then the self intermediate scattering function will be computed at nearest rounded integer time points 0, $1.5^0(1)$, $1.5^1(2)$, $1.5^2(2)$, $1.5^3(3)$, ... , 1.5^n .

k_start_index

- [default: 0, optional] This value determines the first multiple of δk used, where $\delta k = 2*\pi/\text{boxlength}$.

number_of_bins

- [default: 50, optional] This sets the number of multiples of δk where the self intermediate scattering function will be calculated at, starting from kstartindex and ending at kstartindex + numberofbins.

6.11 Coherent Intermediate Scattering Function: $F(k, t)$

User can input selected atom types using only the **atom_types** parameter. Scattering lengths can be provided in order of atom types to compare with experiments.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the self intermediate scattering function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Self intermediate scattering function can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the time_scale is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the self intermediate scattering function to be computed every .2 ps, this value should be set to 2.
- If the time_scale is set to “log”, this value determines the base of the scaling for calculating the self intermediate scattering function. For example, if this value is set to 1.5, then the self intermediate scattering function will be computed at nearest rounded integer time points $0, 1.5^0(1), 1.5^1(2), 1.5^2(2), 1.5^3(3), \dots, 1.5^n$.

k_start_index

- [default: 0, optional] This value determines the first multiple of δk used, where $\delta k = 2*\pi/\text{boxlength}$.

number_of_bins

- [default: 50, optional] This sets the number of multiples of δk where the self intermediate scattering function will be calculated at, starting from kstartindex and ending at kstartindex + numberofbins.

6.12 Bond Order Parameter: $q_l(i, t)$, $\bar{q}_l(i, t)$, $Q_l(t)$

User can input selected atom types using only the **atom_types** parameter.

number_of_time_points

- [default: 0, optional] This is the number of points that will be calculated for the self intermediate scattering function. If this value is not included it will be derived from the number of frames provided and the number of frames to average.

time_scale_type

- [default: linear, optional] This can be set to “linear” or “log”. This sets the time scale of the output. Self intermediate scattering function can either be computed in linear scale or log scale, log scale allows for a quicker calculation if the trajectory is very long (i.e. longer than 10000 time steps).

frame_interval

- [default: 1, optional] This value has two meanings. If the time_scale is set to “linear”, this value should be an integer greater to or equal to 1, and sets how many time steps between each data point to skip. For example, if the trajectory has a timestep of .1 ps, and you wish for the self intermediate scattering function to be computed every .2 ps, this value should be set to 2.
- If the time_scale is set to “log”, this value determines the base of the scaling for calculating the self intermediate scattering function. For example, if this value is set to 1.5, then the self intermediate scattering function will be computed at nearest rounded integer time points $0, 1.5^0(1), 1.5^1(2), 1.5^2(2), 1.5^3(3), \dots, 1.5^n$.

is_averaged

- [default: no, optional] This is a boolean value. Available options include, no, yes, false, true, or a integer numeric. 0 is considered false, and any other numerical value is considered true. This value determines whether the bond order parameter is calculated per atom or per the system. If false, the bond order parameter is calculated for each atom, if true the bond order parameter is calculated for the system at each frame.

add_bar

- [default: no, optional] This is a boolean value. Available options include, no, yes, false, true, or a integer numeric. 0 is considered false, and any other numerical value is considered true. This value determines whether the bond order parameter is calculated or if the nearest neighbor averaged bond order parameter is calculated. If false, the bond order parameter is calculated. If true, the nearest neighbor averaged bond order parameter is calculated.

bond_parameter_order

- [required] This value sets the order, l , of the bond order parameter. A non-negative integer is required for this option. This determines if say q_6 or q_4 is calculated

max_cutoff

- [required] This value sets the distance to search for nearest neighbors. This should be set to the first minimum of the pair distribution function.

7 Common Errors

ERROR: the trajectory file: FILENAME does not exist.

This means that the trajectory file provided in the input file failed to be opened. Most likely this means the path was incorrectly provided, there is read protection on the file that prevents opening, or an incompatible file type was provided.

ERROR: the gro file: FILENAME does not exist.

This means that the .gro file provided in the input file failed to be opened. Most likely this means the path was incorrectly provided, there is read protection on the file that prevents opening, or an incompatible file type was provided..

ERROR: .trr files are not compatible in non GROMACS compatible version of LiquidLib.

This means that a .trr or .xtc trajectory file was provided but *LiquidLib* was not built with the necessary header files and library provided. If you attempted to build a GROMACS version and still obtained this error, this means that the paths provided in the Makefile are most likely incorrect and should be checked.

ERROR: The trajectory file type: .EXTENSION does not match any known type

At this time, only .xtc, .trr, .xyz, .dump, .atom, and XDATCAR files can be provided. We use these extensions to determine how to read in the trajectory, so we require this extension type. We plan to expand on this option in future releases.

ERROR: unrecognized atom type/group "BLANK"

This means that the string provided for the atomtype or atomgroup option in the input file did not match any type in the trajectory or .gro files provided. At this point, only system, all, solvent, or non-solvent can be provided to the group option. Maybe check the letter case for consistency or spelling.

ERROR: Failed to read trajectory, please check the total number of frames

This occurs usually when the number of frames needed to be read exceeds the number of frames in the trajectory file. If this occurs check the values of endframe, startframe, and numberofframestoaverage to see that they do not add to a value in excess of the number of frames in the trajectory.

ERROR: The amount of memory to store all of the frames exceeds memory allotment

There is currently no fix to this problem other than to decrease the number of frames you are attempting to read in from a trajectory file and use for the computation. Improvements for reading very large trajectory files will be made in future releases to mitigate such memory issues.

ERROR: Input file location, BLANK does not exist, please check input

The input file provided at the command line does not exist. Most likely this is an incorrect path problem.

ERROR: Output file for “QUANTITY”: FILENAME could not be opened

This means that the output file could not be opened. This most likely occurred due to inadequate write privilege or the path to the file does not exist. Liquidlib cannot create directories if they do not exist. Hence, the output file path must exist.

ERROR: Require more information to proceed

This error is to inform the user that program execution cannot continue without either mandatory parameters provided. For instance, frameend or numberoftimepoints provided in the input file for a time dependent quantity. We need this to determine how many data points along the time dimension should be created. One can be derived from the other, like wise, if both are provided numberoftimepoints will take precedence.

WARNING: no matching input type for: VARIABLE disregarding this variable

This means one of the options in the input file does not match one of our check variables for the given quantity. Most likely this would result from a typo or a case inconsistency, remember program requires use of all lower case letters.

WARNING: time step of simulation could not be derived from trajectory

This merely means that the time step was not provided in the input file and could not be extracted from the trajectory, thus program will set the trajectory Δt to 1 arbitrary step or a.u. This warning is to inform the user to be cautious with the output since the units are arbitrary.

WARNING: number of frames required is greater then the number supplied

This means that the number of frames needed to compute the numberoftimepoints specified is greater than that given by frameend and framestart. Thus program will change the value of endframe to allow for the necessary number of frames. Note this may still lead to needing more frames then are in the trajectory and thus an error will be thrown in this instance.

WARNING: max cutoff is greater than half of the boxlength

The pair distribution function cannot be computed for values of $|r|$ greater than half the boxlength, the statistics are not accurate past this point. Thus program will reset the maxcutoff to be half of the smallest boxlength of all dimensions.